


myRIO Dynamic Signal Analyzer Documentation

I) Overview:

A) The myRIO Dynamic Signal Analyzer (DSA) is designed to be used as a subVI (**Dropable_DSA.vi**) that can be simply dropped into new and/or existing control and/or simulation code to measure a desired frequency response and plot it as the corresponding Bode plots.

B) DSA Inputs/Outputs:



1. Inputs:

a) Excitation Specs [Cluster]

i) Initial Frequency [Double]

(1) The lowest frequency of the frequency range which the DSA will measure the bode plot for.

ii) Final Frequency [Double]

(1) The highest frequency of the frequency range which the DSA will measure the bode plot for.

iii) Frequency Units [Boolean]

(1) Whether the frequency range input is in Hz or rads/sec.

(2) TRUE = Hz | FALSE = rads/sec

iv) Number of Frequencies [Integer]

(1) The number of logarithmically spaced frequencies to measure the bode plot for.

v) Sampling Time [Double]

(1) The time step taking in between each measurement.

(2) $\text{Sampling Time} = 1/\text{Sampling Rate}$

vi) Amplitude [Double]

(1) Amplitude of desired swept sine excitation.

vii) Offset [Double]

(1) DC offset of swept sine excitation.


- b) Cycle Specs **[Cluster]**
 - i) Cycles to Settle **[Integer]**
 - (1) The number of cycles of the swept sine wave at each frequency to ignore to let the transient response die out.
 - ii) Cycles to Calculate **[Integer]**
 - (1) The number of cycles of the swept sine wave at each frequency to measure in order to measure the bode plot.
- c) Controls:
 - i) START **[Boolean]**
 - (1) Tells the DSA to initialize and then start.
 - (2) **TRUE = Start/Restart and initialize the DSA | FALSE = Nothing**
 - ii) STOP **[Boolean]**
 - (1) Tells the DSA to stop and set all analog outputs to zero.
 - (2) **TRUE = Stop the DSA | FALSE = Nothing**
 - iii) EXIT PROGRAM **[Boolean]**
 - (1) Tells LabVIEW to set all analog outputs to zero and exit the program.
 - (2) **TRUE = Stop the DSA & execute exit program code | FALSE = Nothing**

2. Outputs:


- a) Running **[Boolean]**
 - i) Signal to show if the DSA is running.
 - ii) **TRUE = Tells the DSA to keep running (since start is an initialize button) | FALSE = Nothing**
- b) Stopped **[Boolean]**
 - i) Signal to show if the DSA is stopped (Visual counterpart to Running)
 - ii) **TRUE = Indicates that the DSA has stopped | FALSE = Nothing**
- c) FINISHED LATE **[Boolean]**
 - i) Signal to show if the DSA is running slower than the desired sampling rate.
 - ii) **TRUE = Indicates the myRIO cannot keep up with the desired sampling rate | FALSE = Nothing**
- d) Bode Magnitude **[Cluster]**
 - i) The magnitude plot of the TF CH1/CH0.
 - (1) x = List of Frequencies **[Array of Doubles]**
 - (2) y = List of Magnitudes **[Array of Doubles]**
- e) Bode Phase **[Cluster]**
 - i) The phase plot of the TF CH1/CH0.
 - (1) x = List of Frequencies **[Array of Doubles]**
 - (2) y = List of Phases **[Array of Doubles]**

C) Example Code

1. Stand-Alone DSA: Example code on how to use the Dropable_DSA.vi inside a timed while loop.



2. Embedded DSA: Example code on how to use the Dropable_DSA.vi with a simulated controller.



II) Code Internal Structure

A) For the internal code structure. see the documentation (help) for each subVI.